

VOLTA

ALERT PRO Firmware Update



Product	ALERT PRO (all models)
Version	VOLTA #5263
Replaces	All earlier releases
Date	24/11/2023
Reason for Update	Functionality improvements

Summary of Changes

- Support for over-the-air updates with CONNECTED units
- System diagnostics to improve in-the-field support

Installation of Firmware

1. Save the installation ".hex" file to a USB memory stick. Make sure that there are no other ".hex" files on the stick.
2. Insert the USB stick into the USB slot on the metal top plate of the Alert PRO unit.
3. From the main menu navigate to the upgrade option:
 - Main Menu
 - 5. Settings
 - 4. Administration
 - Enter your administration PIN (default is 1234)
 - 3. Firmware Update
 - ENTER to confirm
4. Please wait while the system copies the file from the USB and updates the system. This can take several minutes
5. The system will restart and show the new version on the start-up screen.
6. To confirm that the new version is installed
 - Main Menu
 - 3. System Info
 - 1. Version Info